How to Remove Windows Partition

How to remove a windows partition from you Macintosh computer.

- Navigate to and open "Disk Utility"
 - Macintosh HD > Applications > Utilities > Disk Utility

	Firs	8일 (Delta) st Aid Partition E	rase Unmount	(j) Info			
Internal APPLE HDD HTS APPLE HDD HTS Macintosh HD BOOTCAMP	Macintosh HD 250,05 GB SATA Internal Physical Volume OS X Extended						
	• Apps 8,2 GB	Photos 906,3 MB	Audio 1,67 GB	Movies 46,8 MB	Other 8,53 GB	Available 230,7 GB	
	Mount Point:		1	Type:	SATA Interna	al Physical Volume	
	Capacity:		250,05 GB	Available:		230,7 GB	
	Used: 19,35 GB			Owners: Enabled			
	Device:		disk0s2	Connection:		SATA	

- Click on the hard drive icon highlighted in red as below.

	First Aid Partitio	on Erase Mount	Info		
ternal APPLE HDD HTS Macintosh HD BOOTCAMP	APPLE HDD HTS545050A7E362 Media 500,11 GB SATA Internal Physical Disk				
	Macintosh HD 250,7 GB		 BOOTCAMP 249,19 GB 		
	Location:	Internal	Capacity:	500,11 GB	
	Connection:	SATA	Child count:	4 Dick	
	S.M.A.R.T. status:	Verified	Device:	disk0	

- Click on the Partition icon next to disk first aid
- Click on the partition relating to your windows installation (often called Boot Camp)
 - Then click on the icon to remove the windows partition and click apply.

ernal				
APPLE H	Partition To resize a	device "APPLE HDD partition on the selected	HT\$545050A7E362 Media"? I disk, drag its resize control and press Apply.	а
BOOT	×	Dovice	aformation	
249 GB		Device		
		Cohomo		
		Bertitier		
	249 GB 2	51 GB	Information	
		Partition	BOOTCAMP	
		Format	OS X Extended (Journaled)	
		Size	249,194 GB ᅌ	500,11 GB
				4
	(+ -	-	Cancel Apply	Disk
_	S.M.A.R.T. Status:		vermed + Device:	disk0